


# Audiocorder

Audiocorder Version 5.1.0 March 18, 2007



## Requirements

Mac OS X 10.3 or later. Audiocorder is distributed as a universal binary, and will work on both PowerPC and Intel Macintosh systems. If you have Mac OS 9 or an Mac OS X 10.2.8 or earlier, you need to use version 4.x of Audiocorder, available from the website.

info@blackcatsystems.com  
<http://www.blackcatsystems.com>

## Notes

Thanks for giving Audiocorder a try. Please read through these brief instructions, so you'll be able to fully utilize Audiocorder's features. Please also take a moment to read the section of registering (paying for) your copy of Audiocorder.

## Requirements

A Macintosh with built in sound input, or a USB sound input device. The sound input device must be capable of recording at 44.1 kHz, 16 bits, mono or stereo. If not, Audiocorder will not work properly. Some of the more basic USB microphones cannot record at 44.1 kHz, resulting in a chipmunk like recording. The Griffin iMic USB mike works fine.

Audiocorder for Mac OS X requires at least version 10.3.0 of Mac OS X. If you have an earlier version of Mac OS X, or are running Mac OS 9, please instead download an earlier version of Audiocorder, available on our download page:

<http://www.blackcatsystems.com/download/audiocorder.html>

## Introduction

Audiocorder allows you to record sound using your Mac.

You can do this several ways:

Audiocorder can be used to automatically start recording sound to a disk file. The recording process is triggered when the volume exceeds an initial threshold, for a specified minimum amount of time. It then continues to record until the volume drops below a second threshold for a minimum amount of time.

Audiocorder can also be used as a manually operated recorder. You use pushbuttons, just like on a "real" recorder, to start and stop recording.

In addition, Audiocorder can start and stop recording at scheduled times. Up to 50 recording periods may be scheduled in advance. Think of it like a VCR.

You can also use Audiocorder to record telephone calls, if your Macintosh has an internal modem connected to your phone line. **This works with most but not all internal modems. You need to test it on your particular system to see if it will work for you, as not all Macs have the modem audio routed to the sound input device.**

Each sound file is stored in AIFF format, a Macintosh standard sound format, or as a Windows WAVE file. The audio can be sampled at 11, 22 or 44 kHz, with 8 or 16 bit resolution, either monophonic or stereo (depending on your particular Mac's hardware capabilities). The name of


each file contains the date and time (down to seconds) the recording began.

## Start Up

When you first launch Audiocorder, you'll see the Audiocorder window. You'll see a moving bargraph, showing the audio volume levels being recorded (if there's anything to record!)

You'll most likely want to select which audio input device and source to use, along with some other settings. These are explained in the following pages.

## Audiocorder Window



The main window contains a volume indicator, five slider controls, five or six buttons, and a bar graph showing past volumes, as well as six popup menus.

## Volume Indicator

This shows the current volume, which can range from 0 to 100%. It is one of three colors:

**Green:** Audiocorder is not recording.

**Yellow:** Audiocorder is currently recording.

**Red:** The volume is too loud, and some of the sound may be clipped, resulting in distortion. Lower the volume control on your radio, or whatever is the source of the audio signal, or adjust the input gain slider.

## Manual Recording

There are four buttons in the lower right corner, under the volume sliders. Two (on the left) have a red dot, and allow you to manually start recording, regardless of the volume level. The other two are the stop button (it has a black square), stops a manually started recording, and the pause button, which pauses recording.

The two record buttons behave in slightly different ways. The one next to the stop button works just like you would expect, when clicked it starts recording. The other one, buffered record, also records the audio present just before the button was clicked as well. The length of the additional buffered audio is specified in the preferences for Audiocorder as the “Buffer time” in seconds, and may range up to 60 seconds.

You can also use the menu commands under the File menu to start stop recording, or their keyboard shortcuts.

When in VOX mode, the stop button will also stop recording. If the volume is above the start threshold, then a new recording will of course start immediately.

## Play Thru

You can enable or disable play-thru by using the button in the lower right corner. Play-thru causes the input sound to be played through your Mac’s speakers. Note that not all Macs support play thru, and not all USB devices do either. Under OSX, play thru does not appear to work with USB microphones.

## AGC

This enables AGC - Automatic Gain Control, which adjusts the input gain based on the audio volume. Not all Macintosh models support AGC, so it may have no effect on your Mac.

## iTunes

If this button is clicked, when a recording ends, iTunes will automatically be asked to place it into it’s Library, as well possibly convert it to mp3 format.

This feature can be used to have iTunes automatically convert a recording into an mp3 format file. Make sure that you have the Import Using set to MP3 Encoder in the Importing preferences pane in iTunes.

It’s recommended that you manually start up iTunes prior to recording, so that it won’t have to start up when the recording finishes.

## Telephone Line

The telephone line button instructs Audiocorder to pick up the phone line, and allows you to record telephone calls. See the section further down detailing this.

## Scissors - Stop/Start Recording

When clicked, this button will stop the current recording, and start a new recording. This is ideal for manually breaking an album or CD into individual tracks. This button is only enabled when you're recording.

## Grab Button

The grab button lets you record sound that has just occurred. Audiocorder continuously buffers (stores) audio. When the grab button is clicked, a portion of that buffered audio is written out as the recording file. The length of that recorded audio is set in the preferences as the "Buffer time" in seconds.

## Volume Operated (VOX) Recording

The VOX button enables or disables VOX recording. When enabled, recording will start and stop as controlled by four slider controls, as explained below.

## Slider Controls

The **Input Gain** slider control can be used to adjust the input volume level, over a small range (as allowed by your Macintosh model)

There are four slider controls which are used to set the conditions that cause Audiocorder to start or stop recording:

**Start Volume:** When the audio volume exceeds this threshold (for a minimum amount of time, see below), recording begins.

**Stop Volume:** When the audio volume is below this threshold (for a minimum amount of time, see below), recording ends.

**Start Trigger Length:** This sets the minimum amount of time (in seconds) the volume must exceed the Start Volume setting for recording to begin. This could be used to reject short bursts of noise, which would otherwise start a recording.

**Stop Trigger Length:** This sets the minimum amount of time (in seconds) the volume must drop below the Stop Volume setting for recording to end. This could be used to allow for short periods of low volume (such as between words), which would otherwise stop a recording.

When you quit Audiocorder, your settings are preserved, and will be used the next time you run the program.

## Voice Vox

When this button is clicked, the “Voice VOX” feature is enabled. This feature tries to use the content of the audio to determine when voice or music is present, vs static and other noises. It can be used to record audio off of a radio when static is present when there is no station on the air, such as some shortwave/ham radio monitoring applications.

It will take a bit of trial and error to learn how to use it. It adjusts the apparent volume based on the content of the audio. The idea is that human speech and music have certain common characteristics. When these are detected, the apparent input volume, as displayed in the volume indicator, and used by VOX mode to trigger the start of a recording, is increased. If the VOX start/stop triggers are carefully adjusted, it is possible to set Audiocorder up to record when there is speech or music present, vs just static, even if the volume of the static is louder than the real programming.

Of course this feature is not foolproof, as it has to make a lot of assumptions about the audio. But it can be useful in many cases.

## Bar Graph

This shows the volume level over the last minute, one second per bar. Each bar is either green or yellow, depending on whether or not Audiocorder was recording at that time. It can be used to see what the average volume level is, and assist you in setting the Start and End volumes.

## Input Source

You can select the input source (such as internal microphone, modem, external input, etc) from the popup menu in the lower left corner of the Audiocorder window.

## Input Device

You can select the input device (such as built in audio, an external USB microphone, etc) from the popup menu located just above the input source menu.

## Sampling Rate

This is the number of samples that are recorded per second. Faster sampling rates sound better, but take up more disk space. 44100 Hz is the sampling rate used by audio compact discs. 22050 and 11025 Hz rates are also available, they have lower audio quality, but also produce smaller files.

## Sample Size

This is the number of bits used to represent each sound sample. 16 bits (used by audio compact discs) sounds best, but takes twice as much disk space as 8 bits.

## Mono / Stereo

Specifies whether the recorded sound should be monophonic or stereo.

Please note that you cannot change the sampling rate, size, or mono/stereo while recording.

## File Format

You can select AIFF or WAVE file formats. AIFF files are used on the Macintosh, and are ideal for using later to burn CDs. WAVE files are commonly used on Windows systems.

## Selecting The Folder To Store Recordings

By selecting **Select Storage Folder...** from the **File** menu, you can choose the folder in which Audicorder saves AIFF recording files. Highlight the folder of interest, and click on Select (or Choose under MacOS 8 or 9). Quit and re-start Audicorder for the change to take effect.

## File names

Each recording is saved as a separate file, with a filename depending on the date and time the recording begins.

A typical automated file name is:

Recording 04-07-2001 191453

This means that the recording was made on 4-7-2001, starting at 19:14:53 (or 7:14:53 PM).


You can always rename a file in the Finder, after recording it.

If you prefer to have multiple recordings saved to one file, select **Record To One File As...** from the **File** menu. Enter the name for the recording file. All subsequent recordings are saved to this file, with each new recording appended to the end. Select **Stop Recording To One File** to resume saving each recording to it's own time stamped file.

## Timed Recording

You can tell Audiocorder to record for a specified length of time, and then stop recording.

Click on the button with a picture of a stopwatch, and you will be prompted to enter the number of seconds of audio to record:



Enter the number of seconds, click OK, and Audiocorder will then start recording, and automatically stop when that number of seconds of audio has been recorded.

## Scheduled Recording

It's possible for Audiocorder to automatically start and stop recording at scheduled times, rather than based on the volume level. To do so, you simply need to create a schedule, and tell Audiocorder to use that schedule.



If you name that schedule file STARTUP, and place it in the same folder as Audiocorder, it will automatically be opened when Audiocorder starts up.

To create a schedule, select new Schedule from the File menu. Each schedule can have up to 50 entries in it. Each entry tells Audiocorder when to start and stop recording. To create an entry, push the New Entry button, and fill out the requested information. If you check the Any date checkbox, then whenever you load this schedule file, the current date will be used. That means that you don't need to edit a schedule file that you wish to use on subsequent days, if you want to record during the same time period.

You can edit an existing entry by double clicking it. You can delete an entry by selecting it, and then clicking on the Delete Entry button.

To pick a schedule file, select Open Schedule from the File menu. Choose the file. The Recording Schedule window will be displayed, showing the recordings that will take place. Next to each recording is a status, which is one of the following:

Queued - The recording is scheduled to occur at the indicated time.

Recording - The recording is occurring now.

Recorded - The schedule has already been recored.

Skipped - The date and time of the entry is earlier than time the schedule was opened, so it wasn't possible to make the recording, and it was skipped.

You can also manually create a schedule file with a text editor, if for some reason you wish to. The schedule is a text file, created with Simple Text or another text editor, but not with a word processor, unless you've saved the file as a plain text file. If you'd like to create a schedule by hand, you can do so. The format of the file is as follows:

Each scheduled recording is listed on one line. The date and time that the recording begins, and then ends, are on that line. For example, to start recording at 5:30 pm on November 7, 1999, and stop recording at 5:45 pm on November 7, 1999, the line would look like this:


```
11/7/1999 1730 11/7/1999 1745
```

You can have up to 50 such lines in your file, allowing for up to 50 recordings to take place. The recording filename follows the standard Audiocorder format. It's important to make sure that scheduled recordings are listed in chronological order.

It's also important to make sure that each line ends with a return.

With files created using a text editor, you can place an asterisk in place of each of the dates, and Audiocorder will substitute today's date when it reads in the file. Note that this can **only** be done with text file schedules you create, not with schedules created within Audiocorder.

## Schedule Window:




A screenshot of a 'Schedule Window' with a title bar containing three colored buttons (red, yellow, green) and the text 'Schedule Window'. The window contains a list box titled 'Schedule' with the following entries:

Schedule		
2/19/2007, 14:00:00 to 2/19/2007, 14:30:00	Skipped	3
2/19/2007, 20:00:00 to 2/19/2007, 21:00:00	Queued	3
2/20/2007, 10:00:00 to 2/20/2007, 22:45:00	Queued	3

New Entry

Delete Entry



A screenshot of an 'Entry Window' with a title bar containing the text 'Entry Window'. The window contains the following fields and controls:

Start:

End:

☒ Any date

## Recording Telephone Calls

If you have an internal modem, and it is connected to your phone line, you can use Audiocorder to record phone calls. Select the Internal Modem as the input source in the popup menu in the lower left corner of the Audiocorder window. **This works with most but not all internal modems. You need to test it on your particular system to see if it will work for you, as not all Macs have the modem audio routed to the sound input device.**

When you want to record a call, click on the button with a telephone symbol on it. Audiocorder will then tell the modem to pick up the phone line. You can then manually record, or use the automated recording, to actually start and stop the recording process. When done, click on the phone button again, and Audiocorder will release the phone line. Please note that clicking on the phone button only tells the modem to pick up the phone line, it doesn't actually start the recording process.


If you don't see the telephone button, make sure that you have Check For Modem enabled in the Recording Settings, and your Macintosh actually has an internal modem capable of routing audio as the input device. For example, this will not work on the iBook (and certain other Mac models as well), as the sound from the internal modem is not available for recording. Apparently this is also the cause on certain G3 desktop models. This is a hardware problem, and cannot be fixed with software!

You can script Audiocorder using Applescript to do some interesting things with the modem. You can use the SetModem command to put the modem off or on hook (pick up the phone line). You can also use the DialDigits command to have the modem produce DTMF (Touch Tone) digits. This can be useful to dial a certain phone number, enter digits to navigate a voice mail system menu, etc. If you need to set delays, you will need to use the delay feature in Applescript, please see any books or other documentation on Applescript for details on how to do this.

Please be sure to check with your local laws regulating the legality of recording telephone conversations!

## Preferences / Recording Settings

By selecting **Recording Settings...** from the **File** menu (or Preferences under OS X), you can choose the sampling rate, word size, etc. These are much more easily chosen by using the pop-up menus on the main Audiocorder window. You can also select the creator ID for sound files, which allows you to specify which application should be launched if you double click on the sound file icon. You'll be presented with a display similar to this one:



These are the values you can select:

### Creator ID:

Sets the Creator ID for recording files. When a recording file is double clicked, the Creator ID is used by the MacOS to select which application to run to open the file. This allows you to choose which program should play any recording files produced by Audiocorder.

### Buffer Time:

When using the buffered record mode, this field specifies the number of seconds of audio from

the time before the recording started, which should be prepended to the beginning of the recording file.

When using the grab mode, it specifies the number of seconds of audio to be written to the recording file.

### **Max Length:**

If this value is non zero, it specifies the maximum length of a recording, in seconds, when time-stamped recording files are used. Once this length is reached, the current file will be closed, and a new file will be opened.

### **Hour Offset:**

When timestamped filenames are used, this field specifies an offset (in hours) added to the timestamp, it can be used to convert local time to UTC, for example.

### **Check For Modem:**

When clicked, Audiocorder will check for the presence of a modem when it starts up.

### **Software Gain:**

When clicked, the input gain slider will be used to amplify the signal in software. The actual hardware gain, if any, is set to one. This is useful for recording from input devices that do not support variable gain, such as the iMic presently under OS X. Since the amplification is being done in software, the dynamic range will be reduced, and the quality will suffer as the input sound level is lower and more gain is used.

### **Mono Input Device:**

Make sure this is selected if a monophonic input device is being used. Many USB microphones fall into this category. If incorrectly selected/not selected, garbled recordings will result. If your recordings seem to be too fast (double speed, high pitched) you probably have this enabled when it shouldn't be. As of version 3.9.0, this will be automatically checked or cleared when a USB input device is selected.

### **Timestamp VOX Recordings:**

When checked, a voice generated timestamp will be added to the beginning of each VOX started recording. Works under OSX 10.3 or later only.

### **Timestamp Manual Recordings:**

When checked, a voice generated timestamp will be added to the beginning of each manually started recording. Works under OSX 10.3 or later only.

**Include date in timestamp:**

When checked, the voice timestamp will include the date. Works under OSX 10.3 or later only.

**Include seconds in timestamp:**

When checked, the voice timestamp will include the seconds. Works under OSX 10.3 or later only.

**Add extension to recordings:**

When checked, timestamped recordings will have either .WAV or .AIF added to the end of the filename.

## Playing Back Last Recording

You can play back your last recording by selecting **Play Last Recording** from the **File** menu.

Select your file from the Open File dialog, and Quicktime player will be opened to play the file.

## Applescript Commands

You can control most of Audiocorder's features using Applescript. Below is a brief description of each scripting command available:

**Filename:** Specify name of single file to record to

**Filename** file specification -- *FSSpec for file*

**StopRecordingToOneFile:** Go back to recording to timestamped filenames

**StopRecordingToOneFile**

**PlayFile:** Play a recorded file

**PlayFile** file specification -- *FSSpec of recording file to play*

**PlayThru:** 0 to disable playThru, 1 to enable

**PlayThru** integer

**StartVolume:** 0-100 volume to start VOX recording

**StartVolume** integer -- *0-100*

**StopVolume:** 0-100 volume to stop VOX recording

**StopVolume** integer -- *0-100*

**Agc:** 0 to disable AGC, 1 to enable

**Agc** integer -- *0 to 1*

**Record:** Start recording

**Record**

**Vox:** 0 to disable VOX, 1 to enable

**Vox** integer -- *0 or 1*

**StopTime:** 0-10 seconds VOX stop time

**StopTime** integer -- *0-10*

**StartTime:**

**StartTime** integer -- *0-10*

**Unpause:** stop pause, re-start recording

**Unpause**

**SampleRate:** 11025, 22050, or 44100 Hz

**SampleRate** integer

**SampleSize:** 8 or 16 bits

**SampleSize** integer



**SampleCh:** 1 (Mono) or 2 (Stereo)

SampleCh integer

**SetDevice:** Set audio input device

SetDevice string

**SetSource:** Set audio input source

SetSource string

**GetDevices:** Get a comma delimited list of all devices

GetDevices

Result: string

**GetSources:** Get a comma delimited list of all sources for the active device

GetSources

Result: string

**Format:** AIFF or WAVE

Format string

**GetDevice:** Get name of current sound input device

GetDevice

Result: string

**GetSource:** Get name of current sound input source

GetSource

Result: string

**StopRecording:** Stop Recording

StopRecording

**Pause:** Pause Recording

Pause

**GetVolume:** Returns current volume, 0-100

GetVolume

Result: integer

**GetRecordingTime:** Get current recording time (length) in seconds

GetRecordingTime

Result: integer

**GetStatus:** Returns recording status - OFF or ON or PAUSED

GetStatus

Result: string

**Gain:** 0-100 Audio input gain

**Gain** integer -- *gain setting 0-100*

**TimedRecording:** Start a timed recording

**TimedRecording** integer -- *seconds*

**SetModem:** 0 (On Hookj) or 1 (OffHook)

**SetModem** integer

**DialDigits:** Digits to dial

**DialDigits** string

## Troubleshooting

If the recording playback speed sounds too fast, check to see if you have a monophonic USB microphone or input device. If so, be sure to check the box for monophonic input device in the preferences. Likewise, if the playback speed sounds too slow, check to see that you didn't accidentally check that box when you should not have.

Please see the next chapter of this document for information on registering your copy of Audiocorder, which will remove the reminder message at the beginning of each recording.

## Buying Audiocorder

Audiocorder is distributed as shareware. If you find Audiocorder useful, please buy your copy. When you purchase, Audiocorder will not prepend a short reminder message in every audio file recorded. You can pay by check or money order by printing out the form on the following page, or you can buy your copy of Audiocorder online, by visiting:

<http://www.blackcatsystems.com/register/audiocorder.html>

Please note that Audiocorder is in no other way crippled. If you can't make a recording, or the recording sounds garbled, then there is a problem preventing Audiocorder from properly running on your system. Registering it won't fix this problem!

Your purchase entitles you to all upgrades of Audiocorder released within one year of your registration. So you'll get all the new features and any bug fixes.

By buying your copy of Audiocorder, you'll help support my efforts to develop newer versions, and the features available. I'd like to be able to continue developing new versions of Audiocorder, so that we Mac users won't be forced to abandon the Macintosh for the wintel platform.

If you want to use Audiocorder on multiple computers, you'll need to register a copy for each computer. If you'll be using Audiocorder on many computers, you may want to take a look at our site licensing options, which can save you a great deal of money.

When you purchase Audiocorder you'll receive a registration code, by email.

Thanks again for giving Audiocorder a try.

Black Cat Systems  
4708 Trail Court  
Westminster, MD 21158  
USA

email: [info@blackcatsystems.com](mailto:info@blackcatsystems.com)

Web: <http://www.blackcatsystems.com/software/audiocorder.html>

## Order by Check or Money Order Form

To order by check, please fill out and mail the following form, along with your payment. You can pay with a wide variety of cash from different countries but at present if you pay via check, it must be a check or money order drawn in US Dollars from a US bank. While there is the risk of loss in the mail, currency is also OK, including foreign currency.

Please make sure you include your email address with your payment. That way we can send the registration code to you. If you do not send us a valid email address, we have no way to send you the code.

I would like to order \_\_\_\_\_ copies of Audiocorder at \$19.99 US each.

If you'd like a copy of Audiocorder(as well as demos of all of our other programs) on a CDROM, please order one:

I would like to order \_\_\_\_\_ Black Cat Systems CDROMS at \$10 US each. (incl shipping)

Name: \_\_\_\_\_

Address: \_\_\_\_\_

City: \_\_\_\_\_ State/Province:\_\_\_\_\_

ZIP/Postal Code: \_\_\_\_\_ Country: \_\_\_\_\_

Email Address: \_\_\_\_\_

Macintosh Model: \_\_\_\_\_ System Version: \_\_\_\_\_


Enclosed, please find my check / money order / cash in the amount of \$\_\_\_\_\_  
Maryland residents please add 5% sales tax

**Mail this form, along with payment, to:**

**Black Cat Systems  
4708 Trail Court  
Westminster, MD 21158  
USA**

## Entering Your Registration Code

When you register Audiocorder, you'll receive an email containing your registration code. Select **Register...** from the **File** menu, and enter the code into the window that appears, along with your Name and Email address (optional):



The image shows a dialog box titled "Enter Registration Code". It contains two text input fields: "Reg Name:" and "Reg Code:". Below the fields are two buttons: "Cancel" and "OK". The "OK" button is highlighted with a blue gradient. The dialog box has a standard Mac OS X style with a title bar and a close button in the bottom right corner.

## Audiocorder Version History

5.1.0 March 6, 2007

Added Applescript commands to dial DTMF digits via the modem.

Fixed a bug with the Grab feature.

5.0.0 March 6, 2007

First release of Universal Binary version.

5.0.0b1 February 19, 2007

First beta release of Universal Binary version.

4.9.0 October 26, 2006

Added an option to put extension on the filename of automated recordings.

Added a command to play back the last recorded file.

The Playback window is no longer automatically closes when playback is done.

Fixed some bugs with the Playback window.

4.8.0 June 22, 2006

Added voice timestamp feature.

When saving to one file is selected, this setting will be remembered each time you start Audiocorder.

4.7.1 March 14, 2006

Fixed a bug that could cause a crash if the preference file is corrupt.

4.7.0 January 26, 2006

Added voice discrimination VOX recording.

Can now set maximum recording length, new recordings will start when this time is reached.

4.6.0 November 29, 2005

Improved sound quality when recording at 11 and 22 kHz sample rates.

Increased maximum VOX trigger lengths to 20 seconds

4.5.0 September 8, 2005

Added hour offset for timestamp file names

Fixed a bug that caused poorer quality for monophonic recordings.

4.4.0 August 23, 2005

Addressed several Tiger (OS X 10.4) related issues.

4.3.2 May 25, 2005

Recording schedules can now go across midnight.

4.3.1 April 19, 2005

Bug fix, all valid registration codes did not work

#### 4.3.0 April 18, 2005

Added modem recording support to the Mac OS X version.

Grab sound feature no longer clears the buffer when used.

Fixed a bug that caused the wrong storage folder to be used immediately after it was changed.

#### 4.2.1 January 11, 2005

Fixed a memory leak that would cause a crash under Mac OS 8/9 (and eventually in OS X).

#### 4.2.0 December 16, 2004

Added buffered record feature.

Added Grab sound feature.

Fixed input volume indicator bug.

#### 4.1.0 September 9, 2004

Fixed a bug that could prevent the destination folder for saved recordings to be properly used.

Fixed a bug - start and stop recording buttons were not labeled.

#### 4.0.2 April 28, 2004

Fixed a bug that could cause the recording storage folder to not be properly recalled.

#### 4.0.1 March 18, 2004

Fixed a bug with the recording to one file option.

#### 4.0.0 February 12, 2004

Added interface to iTunes

#### 3.9.1 November 7, 2003

Fixed bug - recording volume

Fixed bug - schedule sometimes displayed/used wrong date/time

#### 3.9.0 October 19, 2003

Automatically detects monophonic USB input devices

Fixes to volume display

#### 3.8.0 September 7, 2003

Schedule can use wildcard for date to be used on any day.

#### 3.7.2 June 16, 2003



User interface - made it more clear what the start/stop volume sliders do.

#### 3.7.1 March 30, 2003

Fixed a bug that prevented more than 30 items in recording schedule

Added Applescript commands for timed recording.

#### 3.7.0 February 6, 2003

Added timed recording

Changed / to - in filenames

Fixed a bug where selecting record to one file didn't bring up a Save As dialog.

#### 3.6.2 December 31, 2002

Fixed a bug with Applescript

#### 3.6.0 November 3, 2002

Added scissors button

Playback includes fast forward and rewind buttons, shows elapsed time, volume slider.

#### 3.5.0 October 6, 2002

Added Applescript support

Added pause button to pause recordings

Added scissors button to manually split tracks

Now supports mono input devices (like microphones)

#### 3.4.0 July 21, 2002

Added menu commands and keyboard shortcuts to start/stop manual recording.

#### 3.3.1 April 30, 2002

Misc bug fixes.

#### 3.3.0 March 9, 2002

Release version.

#### 3.3.0b2 March 2, 2002

1. Addition of schedule window

2. Ability to play back recordings added

#### 3.3.0b1 February 10, 2002

1. Several bug fixes

### 3.2.1 January 1, 2002

1. Remind message in unregistered version could sound garbled

### 3.2.0 January 1, 2002

1. Many OSX user interface improvements
2. Ability to change input device selection from the main window
3. Ability to save in WAVE format
4. AGC from the main window
5. Faster updates to the volume indicator

### 3.1.0 August 25, 2001

1. Popup menus added to easily change various settings
2. Ability to change sound input source from within Audiocorder.

### 3.0.0 May 13, 2001

1. Carbon support for MacOSX.

### 2.0.2 January 15, 2001

1. Better support for older versions of MacOS.

### 2.0.0 January 2, 2001

1. Can now record telephone calls from the internal modem.

### 1.9.9 September 29, 2000

1. Recording files are now hidden until the recording is finished.
2. Gain value is now displayed under the slider.

### 1.9.8 August 8, 2000

1. Added the ability to select the folder in which Audiocorder saves AIFF files.

### 1.9.7 July 2, 2000

1. Audiocorder now requires the recording settings to be confirmed if unregistered (to verify they are done the first time the program is run).
2. VOX now defaults to off when Audiocorder is first run.

### 1.9.6 June 30, 2000

1. Fixed a bug where Audiocorder would crash with a Type 4 (Divide By Zero) error if it was run for the first time, and a recording was made before the sound input settings were set.

1.9.5 June 27, 2000

1. Automatically opens schedule called STARTUP if it exists.
2. Doesn't open Recording Settings dialog on launch.

1.9.1 May 15, 2000

1. Bug fix - play-thru did not work on all Mac models.

1.9.0 May 6, 2000

1. Added ability to play AIFF files.

1.8.0 April 1, 2000

1. Added ability to select sound input device.
2. Added ability to set creator ID for recording files.
3. Added ability to change recording settings while Audiocorder is running.
4. Start/Stop buttons are correctly highlighted when in VOX mode.
5. Changed format of filenames to display the date first for better sorting in Finder.
6. Length of recording now correctly displayed for stereo mode.
7. Gracefully exit if the sound input device is already open from another application.

1.7.0 March 9, 2000

1. Added Input Gain.
2. Added VOX button to disable automatic recording.

1.6.1 January 30, 2000

1. If a sound is recording when Audiocorder is quit, it will now finish writing to the file before quitting.

1.6.0 December 12, 1999

1. Added AGC selection.
2. Fixed a bug which caused the very first part of some recordings to not be recorded.

1.5.0 November 11, 1999

Added scheduled recordingd.  
Added manual start/stop recording.

1.3.1 October 8, 1999

Added Audio Play-thru.

1.3.0 September 25, 1999  
Added stereo recording.

1.2.1 May 30, 1999  
Fixed bugs with 16 bit recording, and recording at 11 and 44 kHz.

1.2.0 May 29, 1999  
Added ability to record at different rates and sample sizes.

1.1.0 May 16, 1999  
Added ability to save multiple recordings into one file.

1.0.0  
Initial Release

# Software License Agreement

This is a legal agreement between you and Black Cat Systems, covering your use of Audiocorder (the "Software"). Be sure to read the following agreement before using the Software. BY USING THE SOFTWARE (REGARDLESS IF YOU HAVE REGISTERED THE SOFTWARE OR NOT), YOU ARE AGREEING TO BE BOUND BY THE TERMS OF THIS AGREEMENT. IF YOU DO NOT AGREE TO THE TERMS OF THIS AGREEMENT, DO NOT USE THE SOFTWARE AND DESTROY ALL COPIES IN YOUR POSSESSION.

The Software is owned by Black Cat Systems and is protected by United States copyright laws and international treaty provisions. Therefore, you must treat the Software like any other copyrighted material (e.g., a book or musical recording). Paying the license fee allows you the right to use one copy of the Software on a single computer. You may not network the Software or otherwise use it or make it available for use on more than one computer at the same time. You may not rent or lease the Software, nor may you modify, adapt, translate, reverse engineer, decompile, or disassemble the Software. If you violate any part of this agreement, your right to use this Software terminates automatically and you must then destroy all copies of the Software in your possession.

The Software and its related documentation are provided "AS IS" and without warranty of any kind and Black Cat Systems expressly disclaims all other warranties, expressed or implied, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. Under no circumstances shall Black Cat Systems be liable for any incidental, special, or consequential damages that result from the use or inability to use the Software or related documentation, even if Black Cat Systems has been advised of the possibility of such damages. In no event shall Black Cat Systems's liability exceed the license fee paid, if any.

This Agreement shall be governed by the laws of the State of Maryland. If for any reason a court of competent jurisdiction finds any provision of the Agreement, or portion thereof, to be unenforceable, that provision of the Agreement shall be enforced to the maximum extent permissible so as to effect the intent of the parties, and the remainder of this Agreement shall continue in full force and effect.

The Software and documentation is provided with RESTRICTED RIGHTS. Use, duplication, or disclosure by the Government is subject to restrictions as set forth in subdivision (b)(3)(ii) of the Rights in Technical Data and Computer Software clause as 252.227-7013. Manufacturer is Black Cat Systems., 4708 Trail Court, Westminster, MD 21158, United States of America.

The name "Black Cat Systems", and "Audiocorder" are trademarks of Black Cat Systems.

Audiocorder is ©1998-2007 by Black Cat Systems. All rights reserved worldwide.